NGA-LTER Seward Line CRUISE PLAN Sept 11-25, 2019

Funding Source: NSF, NPRB, EVOS, AOOS, UAF

Chief Scientist: Russ Hopcroft*, Zooplankton, rrhopcroft@alaska.edu Institute of Marine Science University of Alaska Fairbanks, AK 99775-1080 Phone: 907-474-7842 Mobile 907-699-3253

Co-Chief Scientist: Jennifer Questel, Zooplankton, IMS-UAF (JMquestel@alaska.edu)

Scientific Personnel:

3 Emily Stidham
4 Heidi Mendoza-Islas
5 Cara Nelson
6 Kira Monell
7 Kerri Fredrickson
8 Hana Buss
9 Jake Lawlor*
10 Annie Kandell
11 Mette Kaufmann
12 Emily Ortega
13 Rachel Potter
14 Daniel Cushing*

Zooplankton (nights), UAFapplicant Zooplankton (nights), UAF Zooplankton (nights), Teacher-at-sea Zooplankton (days), U Hawaii Phytoplankton/Microzoop, WWU Phytoplankton/Microzoop, WWU Phytoplankton/Microzoop, WWU Chemistry (Nutrients, Iron), UAF Chemistry (Nutrients, Iron), UAF Chemistry (Nutrients, Iron), UAF Chemistry (Nutrients, Iron), UAF Physics (CTD) & UVP, UAF Seabirds/Mammals, FWS

Scientific Purpose:

This cruise represents a continuation of sampling begun in fall 1997 under the NSF/NOAA NE Pacific GLOBEC program, and subsequently a consortium of the North Pacific Research Board (NPRB), the Alaska Ocean Observing System (AOOS), and the Exxon Valdez Oil Spill Trustee Council's (EVOSTC) Gulf Watch. This is the third cruise of the NSF's Northern Gulf of Alaska Long-term Ecological Program (NGA-LTER). The scientific purpose of the core Seward Line project is to develop an understanding of the response and resiliency of this marine ecosystem to climate variability. This cruise marks the 23nd consecutive late-summer cruise for the Seward Line in the NGA, including Prince William Sound (PWS), and the 49th year of observations at GAK1.

Cruise Objectives

- 1. Determine thermohaline, velocity, light, and oxygen structure of the NGA shelf.
- 2. Determine macro- and micro-nutrient structure of the NGA shelf.
- 3. Determine particle structure and flux rates of the NGA shelf.
- 4. Determine phyto- and microzooplankton composition, biomass distribution, and productivity.
- 5. Determine the vertical and horizontal distribution and abundance of zooplankton species (including macro-jellies).
- 6. Conduct surveys of seabirds and Marine Mammals
- 7. Conduct shipboard experimental work on phyto- and zooplankton.
- 8. Determine carbonate chemistry (i.e. Ocean Acidification) at selected intensive stations
- 9. Provide at-sea experience for students within the UAF system
- 10. Share the experience through outreach/media activities.

SAMPLING

The overall approach of the cruise is to occupy 3-4 transect lines across the shelf and a circuit within PWS. Operations are generally divided into distinct day and night tasks, thus requiring each station to be occupied twice. This structure avoids each discipline needing to supply 2 shifts of scientists and ensures all organisms – especially larger diel-migrating zooplankton – are captured with minimal time-of-day bias. During each morning we will typically occupy a selected "intensive" station that involves a greater number and range of collections than other stations occupied that day. Stations profiles are supplemented by underway measurements.

DAYTIME ACTIVITIES:

- 1. Occupy the various hydrographic stations and collect vertical CTD-fluorescence-PAR and particle profiles (see **Figures & Tables**).
- Collect discrete bottle samples at these stations for nutrients, chlorophyll and microzooplankton. Chlorophyll Size Fractionation (20 μm) will be done at all whole numbered Seward Line and most other stations. Macronutrients samples will be pre-filtered prior to freezing. Chlorophyll will be extracted on fresh filters without freezing.
- 3. Measure the dissolved carbonate chemistry along the Seward Line and within Prince William Sound from bottle casts at selected intensive stations (tentatively GAK1, GAK5, GAK9, GAK15, PWS2).
- 4. CalVet Net casts will be done (CalVet frame has 4 nets) after most the CTD casts to 100m. (NO CALVETs at the "i" stations).
- 5. At intensive stations an additional CTD cast will collect water to be used for primary production incubations and carbonate chemistry
- 6. We will deploy a tow-body for sampling near-surface iron during the day (and on long transits). Sampling will occur just prior arriving to or just after departure. (It is hoped that this "fish" can simply be left in the water while on station rather than constantly retrieved and deployed). It is hoped this will not impact transit speed.
- At intensive stations there will be an extra Calvet collection, and along the Seward Line plus PWS2 there will be a vertical deployment of the 150 µm Multinet to 200m. Some of this material will be used for live sorting as well as post-cruise molecular analysis.

8. We will do one deep Multinet tow (to maximum 1200 m) near the end of the Seward Line and one at PWS2 (800m). This normally happens during days but may be done at night in conjunction with Multinet work at those stations if time permits.

NIGHTTIME ACTIVITIES:

- A towed 505-µm Multinet will be used to collected depth-stratified samples along the Seward Line, and at selected PWS Stations to 200m. Bongo nets will be used at all other stations to 200m.
- A Methot Trawl will be deployed by forward crane for ~20 minutes while coming into or leaving stations. We are hoping to get every station with the Methot, but will reduce effort if needed.
- 3. Deep-multinet tows may occur during the night shift as time permits (see #8 above).

Sampling Strategy

In general, we estimate 2 days to complete the Kodiak Line, 1.25 days for Cape Suckling, 2 days for Middleton Island Line, 2.25 days for PWS and 4-5 days for the Seward Line. It is important that all Multinet collections (with the exception of those to 600m) be completed during darkness to allow comparison to prior years. We anticipate that 4-5 Multinet and/or Bongo stations can be conducted per night: sampling starts just after dusk and stops just before dawn, and can be extended slightly when overcast. There is always a much greater period of light available than of darkness, so execution of daytime stations and activities are designed around being in position to commence night sampling as soon as it is sufficiently dark.

Sampling personnel requirements (and times):

CTD: winch operator, 1-2 scientists (launch and recovery), 30m/min in upper 100m, 60m/min below 100m. Depending on schedule, casts may be limited to 1000m at deep-sea stations.

TMC towfish: 1 Deck person and 1 scientist for launch and recovery (~15-20 min), A deck person (or martec) to watch towfish during towing and communicate with the bridge/science.

Multinet or Bongo: winch operator, 2-3 scientists (launch, recovery, wash-down, re-cock) – Ship speed: 2 knots, Wire speed: ~1 m/sec down, 0.5-1m/sec up (typically 30-40min per deployment). Stern A-frame deployment. Maximum depth on tows 200m. Both systems will have depth transducers to ensure we get close to, but not on the bottom when depths are less than 200m.

Calvets & Ring nets: winch operator, 1-2 scientists (launch, recovery, wash-down) – Ship speed: station keeping, Wire speed: ~1 m/sec for Calvet, 0.5m/sec for Ring net (10 min/cast).

Methot Trawl: winch operator, 3-4 scientists, launch, recovery, wash-down) – Ship speed: ~2.5 knots, surface trawl only.

Ship's Science Equipment Supplied:

• Underway sampling system (TSG, GPS) SBE45

Scientist's Equipment Needed:

- CTD (with deep-SUNA, UVP and LISST for integration)
- -40 freezer for macro-nutrient and genetic samples (in hold)
- Trace-metal clean towfish system (access to compress air) (Deck storage 3 palettes)
- Trace Metal Clean Van
- 10 cu ft refrigerator/freezer for chemical and preserved sample storage
- Fume hood for filtration of preserved samples

- CalVet and ring nets [nets, flow-meters, frames, swivels, weights, spares]
- 2 Multinet systems (coarse and fine nets, spare cod ends/nets)
- Bongo nets
- Deckboard incubators (2) connected to ship's seawater system
- Filtration systems
- Fluorometers & Centrifuge
- Laptop computers
- 16 cases (24/cs) of 16-oz zooplankton sample bottles
- 5 cases (12/cs) of 32-oz zooplankton sample bottles
- 3-4 cases of 24 Winkler bottles
- Several coolers with nutrient and TMC bottles
- Microscopes and supplies for sorting copepods
- Incubators: 4 cu ft. required near work area
- Refrigerated Circulators
- Milk Chocolate

Hazmat: (tentative)

Formaldehyde – 2x20L carboy Rose Bengal Stain 50g Ethanol – 40L Acetone – 16L Lugol's solution (1L) Oxygen Fixation (Sodium hydroxide. Sulphuric acid, Manganous Chloride) Mercuric Chloride (for DIC fixation) 3N HCI (25% v/v) (500 ml) Glutaraldehyde (10%) – 500 ml DAPI stain solution – 100 ml Liquid N₂ – one 30-L dewar

CRUISE ACTIVITY SCHEDULE

- 9/10 UAF van leaves ONL 8-9am picks up Petra and heads to Seward. Other members are doing fly/drive with rental cars
- 9/11 Begin setup at ~8am SMC dock, shift shortly thereafter to railway dock for large items then return to SMC. Setup and depart sometime during afternoon.
- 9/25 Reach railway dock for unloading large items by 4pm. Relocate to SMC dock for remaining offload. Ship must be underway by midnight (perhaps earlier) for Homer.
- 9/26 Science party departs for Anchorage and Fairbanks before noon using vans and rentals.

Berthing:

Russ (2-man) Metta, Rachel, Kerri (main deck) Jake, Dan (old library) Jennifer, Emily S., Heidi, Cara (below forward), Annie, Hana, Kira, Emily O. (below aft)


Transport:

Russ' Van: Russ, Jenn, Heidi, Emily O. (down); Kira, Emily S. (ANC-SWD) Rental car: Kerri, Hana, Jake Rental car (ANC-SWD): Mette, Rachel, Annie UHaul (SWD-FAI): Russ Personal transport: Dan, Cara

L	atitude N		itude W	
(degr	ees, minutes)	(degrees	s, minutes)	Station Name
	F	Resurrection Ba	y Station	
60	1.5	149	21.5	RES2.5
		Seward L	ine	
59	50.7	149	28	GAK1
59	46	149	23.8	GAK1I
59	41.5	149	19.6	GAK2
59	37.6	149	15.5	GAK2I
59	33.2	149	11.3	GAK3
59	28.9	149	7.1	GAK3I
59	24.5	149	2.9	GAK4
59	20.1	148	58.7	GAK4I
59	15.7	148	54.5	GAK5
59	11.4	148	50.3	GAK5I
59	7	148	46.2	GAK6
59	2.7	148	42	GAK6I
58	58.3	148	37.8	GAK7
58	52.9	148	33.6	GAK7I
58	48.5	148	29.4	GAK8
58	44.6	148	25.2	GAK8I
58	40.8	148	21	GAK9
58	36.7	148	16.7	GAK9I
58	32.5	148	12.7	GAK10
58	23.3	148	4.3	GAK11
58	14.6	147	56	GAK12
58	5.9	147	47.6	GAK13
57	56.6	147	39	GAK14
57	47.5	147	30	GAK15
	Prin	nce William Sou	Ind Stations	
60	7.5	147	50	KIP0
60	16.7	147	59.2	KIP2
60	22.78	147	56.17	PWS1
60	32.1	147	48.2	PWS2
60	40	147	40	PWS3
60	4925	147	24	PWSA
60	45	147	14	PWSB
60	38.1	147	10	PWSC
60	31.5	147	7.6	PWSD
60	24.3	147	58.3	PWSE
60	24	146	45	PWSF
		Columbia G		
61	7.4	147	3.8	CG0
60	59.5	147	4.2	CG1
60	57.6	147	5.9	CG2

Table 1. STANDARD STATIONS (intensive stations highlighted)

	Icy Bay					
60	16.3	148	21.7	IB0		
60	14.5	148	20.1	IB1		
60	16.3	148	14	IB2		
		16.3 148 21.7 IB0 14.5 148 20.1 IB1				
60	11.57	147	42	HB1		
60	10.754	147	38.5	HB2		
60	9.855	147	34.508	HB3		
60	8.807	147	30.04	HB4		
		Montague Stra	ait Line			
59	57.257	147	55.602	MS1		
59	56.6	147	53.7	MS2		
59	55.9	147	51.4	MS3		
59	55.2	147	49.7	MS4		



Latitude N Longitude W (degrees, minutes) (degrees, minutes) Station Name							
(degrees, minutes) (degrees, minutes) Station Name Kodiak Line							
58	14.7	151	35.4	KOD1			
58	7.8	151	23.07	KOD2			
58	0.9	151	10.74	KOD3			
57	54	150	58.17	KOD4			
57	47.1	150	45.6	KOD5			
57	40.26	150	32.97	KOD6			
57	33.42	150	20.34	KOD7			
57	26.37	150	7.95	KOD8			
57	19.32	149	55.56	KOD9			
57	12.27	149	43.17	KOD10			
		Cape Sucklin	g Line				
59	56.35	143	53.5	CS1			
59	53.85	143	53.5	CS1e			
59	51.35	143	53.5	CS1i			
59	48.85	143	53.5	CS1n			
59	46.35	143	53.5	CS2			
59	41.35	143	53.5	CS2i			
59	36.35	143	53.5	CS3			
59	31.35	143	53.5	CS3.5			
59	26.35	143	53.5	CS4			
59	16.35	143	53.5	CS5			
		Middleton Isla	nd Line	·			
60	15	145	30	MID1			
60	10.5	145	34.5	MID1i			
60	6	145	39	MID2			
60	1.5	145	43.5	MID2i			
59	57	145	48	MID3			
59	52.5	145	52.5	MID3i			
59	48	145	57	MID4			
59	43.5	146	1.5	MID4i			
59	39	146	6	MID5			
59	34.5	146	10.5	MID5i			
59	30	146	15	MID6			
59	25.7	146	10	MID6i			
59	23	146	18	MID7			
59	18.267	146	15	MID7i			
59	13.534	146	12	MID8			
59	4.067	146	6	MID9			
58	54.6	146	0	MID10			

 Table 2. New LTER Stations (intensive stations highlighted)




Fig. 2. NGA-LTER sampling stations highlighting 3 new transects line near Kodiak, Middleton Island and Cape Suckling